

# 1 DH5 ModbusAPI -

## 1.1 Class introduction

DH5ModbusAPI is a Python API based on the Modbus protocol and DH 5 device communication, used to control the initialization, parameter setting and status reading of 6-axis devices.

### 1.1.1 generic attribute

Parameter name	Parameter functions
<b>port</b>	Serial port name, such as `COM6`
<b>modbus_id</b>	Modbus Device ID
<b>baud_rate</b>	Communication baud rate
<b>stop_bits</b>	Stop bit
<b>parity</b>	The verification method supports `N` (no verification), `E` (even verification) and `O` (odd verification)
<b>serial_connection</b>	Serial port connection object

Table 1 Class initialization parameters

Status name	State variable value
SUCCESS	1: Successful execution
ERROR_CONNECTION_FAILED	2: Connection error
ERROR_INVALID_RESPONSE	3: No reply
ERROR_INVALID_COMMAND	4: Input instruction error

## 1.2 Class initialization

```
__init__(port='COM6', modbus_id=1, baud_rate=115200, stop_bits=1, parity='N')
```

Initialize the API instance.

parameter:

- ``port`` (str): Serial port name, default value is ``COM6``.
- ``modbus_id`` (int): Modbus device ID, default value is ``1``.
- ``baud_rate`` (int): Communication baud rate, default value is ``115200``.
- ``stop_bits`` (int): Number of stop bits. The default value is ``1``.
- ``parity`` (str): Verification method, supports ``N``, ``E`` or ``O``, the default value is ``N``.

---

## 1.3 Serial port configuration and instruction sending

### 1.3.1 open\_connection()

Function function:

Open the serial port connection.

returned value:

- Return when successfully opened: SUCCESS.
- If the operation fails, throw an exception and return the reason for failure.

### 1.3.2 close\_connection()

Function function:

Close the serial port connection.

returned value:

- Return SUCCESS when successfully closed.

### 1.3.3 send\_modbus\_command(function\_code, register\_address, data=None, data\_length=None)

Function function:

Send the Modbus command to the DH5 device and receive the response.

input parameter:

1. `function_code`: Modbus function code, supporting `'0x03'` (read register), `'0x06'` (write a single register), and `'0x10'` (write multiple registers).
2. `register_address`: Register address. See the DH5 Smart Hand User Manual. docx for supported register addresses
3. `data` (int or list, optional): The data to be written, the value corresponding to the register address.
4. `data_length`` (int, optional): The number of registers to read or write.

returned value:

- If successful, return the response data of the device.
- If the failure occurs, it returns the `ERROR_INVALID_RESPONSE` and `ERROR_CRC_CHECK_FAILED` error codes. Specific analysis is required.

---

### **1.3.4 `_build_request(function_code,register_address, data_length=1, value=None, values=None)`**

Function:

Build the Modbus request message.

input parameter:

1. `function_code` (int): Function code.
2. `register_address` (int): Register address.
3. `data_length`` (int): The number of registers to read or write, default is ``1``.
4. `value` (int, optional): The value when writing a single register.
5. `values` (list, optional): A list of values when writing to multiple registers.

returned value:

- ``bytearray``: The request message to be built.

### **1.3.5 `_calculate_crc(data)`**

Function:

Calculate the CRC checksum of the Modbus message.

input parameter:

1. ``data`` (bytes): The message data to calculate the CRC.

returned value:

- ``int``: The calculated CRC checksum.

### **1.3.6 `_parse_response(response, function_code)`**

Function:

Parse the response message returned by the device.

input parameter:

1. response (bytes): The received Modbus response message.
2. function\_code (int): The function code used in the request.

returned value:

- If successful, return the parsed data.
- If the failure occurs, ERROR\_INVALID\_RESPONSE and ERROR\_CRC\_CHECK\_FAILED error codes will be returned. Specific analysis is required.

### **1.3.7 set\_config(modbus\_id=None,baud\_rate=None, stop\_bits=None, parity=None)**

Function:

Set serial communication configuration.

input parameter:

1. modbus\_id (int, optional): Modbus device ID.
2. baud\_rate (int, optional): baud rate.
3. stop\_bits (int, optional): The number of stop bits.
4. parity (str, optional): Verification method.

## **1.4 Modbus Parameter configuration**

### **1.4.1 set\_uart\_config(self,modbus\_id=None, baud\_rate=None, stop\_bits=None, parity=None)**

Function:

Configure the UART communication parameters and write them into the relevant registers of the Modbus device.

input parameter:

1. modbus\_id (int, optional): Modbus from device ID.
2. baud\_rate (int, optional): Communication baud rate.
3. stop\_bits (int, optional): Stop bits.
4. parity (int, optional): Verification mode (for example: 0 means no verification, 1 means odd verification, 2 means even verification).

### 1.4.2 set\_save\_param(self, flag = None)

Function:

Set the flag that saves the parameters and write it to the Modbus register address 0x0300.

input parameter:

Flag (int, optional): The flag value to save parameters. For example:

-1 indicates that the current configuration is saved to permanent storage on the device (such as Flash).

-0 means not to save.

## 1.5 initialise

### 1.5.1 initialize(mode)

Function:

Initializes all 6-axis devices at once.

input parameter:

1. mode (int): Initialization mode:
2. `0b01`: Closed initialization.
  - `0b10`: Open initialization.
  - `0b11`: Initialize the total search trip.

returned value:

-Command execution results.

---

### 1.5.2 initialize\_axis(axis, mode)

Function:

Initializes the axis to the specified mode.

input parameter:

1. `axis` (int): The axis number to initialize (1-6).
2. `mode` (int): Initialization mode:
3. `0b01`: Closed initialization.
  - `0b10`: Open initialization.
  - `0b11`: Find the total trip.

returned value:  
-The result of the command execution.

### **1.5.3 check\_initialization()**

Function function:  
Check the initialization status of all six axes.

returned value:  
- `dict`: Initialization state of each axis:  
  - ` "not initialized" `: Not initialized  
  - ` "initialized" `: Initialized  
  - ` "initializing" `: Initialization in progress

## **1.6 Set parameter instructions**

### **1.6.1 set\_axis\_position(axis, position)**

Function function:  
Set the position of the specified axis.

input parameter:  
1. Axis (int): Axis number (1-6).  
2. position (int): Target position.

\*\* returned value:\*\*  
-Command execution result, SUCCESS.

### **1.6.2 set\_axis\_speed(axis, speed)**

Function function:  
Set the speed of the specified axis.

input parameter:  
1. `axis` (int): Axis number (1-6).  
2. `speed` (int): Target speed.

\*\* returned value:\*\*  
-Command execution results.

### **1.6.3 set\_axis\_force(axis, force)**

Function:  
Set the force on the specified axis.

input parameter:  
1. - `axis` (int): Axis number (1-6).  
2. - `force` (int): Target force value.

\*\* returned value:\*\*  
-Command execution results.

## **1.7 Get feedback parameter instructions**

### **1.7.1 get\_axis\_position(axis)**

function:  
Get the position of the specified axis.

input parameter:  
- `axis` (int): Axis number (1-6).

returned value:  
-Location data or error information.

### **1.7.2 get\_axis\_speed(axis)**

function:  
Get the speed of the specified axis.

input parameter:  
1. - `axis` (int): Axis number (1-6).

returned value:

-Speed data or error information.

### **1.7.3 get\_axis\_current(axis)**

function:

Get the current of the specified axis.

input parameter:

- `axis` (int): Axis number (1-6).

returned value:

-Current data or error information.

## **1.8 error handling**

### **1.8.1 get\_history\_faults()**

Function function:

Obtain 21 historical faults.

returned value:

All historical troubleshooting information.

### **1.8.2 get\_cur\_faults()**

Function function:

Obtain the fault status of the device.

returned value:

-Fault data or error information.

### **1.8.3 reset\_faults()**

Function function:

Reset the faulty status of the device.

returned value:

-Command execution results.



## 1.9 instance

Initialize an DH5ModbusAPI instance

```
api = DH5ModbusAPI(port='COM6', baud_rate=115200)
```

```
# interface
```

```
api.open_connection()
```

Initialize the device

```
mode = 0b10 # Open mode
```

```
status = api.initialize(mode)
```

```
if status == api.SUCCESS:
```

```
    Print ("Device initialization successful!")
```

```
Else:
```

```
    Print ("Device initialization failed!")
```

Set the motion position of the axis

```
api.set_axis_position(2, 10)
```

```
api.set_axis_position(3, 10)
```

```
api.set_axis_position(4, 10)
```

```
api.set_axis_position(5, 10)
```

```
api.set_axis_position(1, 500)
```

```
api.set_axis_position(6, 500)
```

Set the speed

```
api.set_axis_speed(1, 10)
```

```
api.set_axis_speed(2, 10)
```

```
api.set_axis_speed(3, 10)
```

```
api.set_axis_speed(4, 10)
```

```
api.set_axis_speed(5, 10)
```

```
api.set_axis_speed(6, 10)
```

Set the force

```
api.set_axis_force(1, 100)
```

```
api.set_axis_force(2, 100)
```

```
api.set_axis_force(3, 100)
```

```
api.set_axis_force(4, 100)
```

```
api.set_axis_force(5, 100)
```

```
api.set_axis_force(6, 100)
```